



VEBKO ONLINE HELP

General Types of Rooms

Category	tester
Section	Software Home Page
Language	English
Generated	2026-10-18

Generally, there are two types of testing rooms available on the main page of the software.

The “VCC” room: this room provides you with a place to perform a series of different tests. Also, it is possible to perform several tests from different rooms in a continuous manner in this room.




Figure 1

The other rooms including “AMT Sequencer”, “AMT Distance”, “AMT Transformer” and “AMT Differential”, have the same main page. The only difference is that in these rooms, a few features are made hidden or shown according to the needs. For example, in the “Hardware” section in the “Sequencer” room, there is an option for “Calibration” but in the same section in the “Distance” room, this option is not available and has been made hidden.




Figure 2

All necessary features for performing different tests are available in the “Sequencer” room. “Table View”, “Detail View” and “Measurement View” are the important windows of this page while the “Table View” and “Measurement View” are not available in the other rooms. Also, the “Detail View” window in this room is different from the “Detail View” in the other rooms like “Distance”.

In rooms like “Overcurrent”, “Distance” and “Differential”, which are also called the “Medium” rooms,

the “Table View” and “Measurement View” windows are not available but instead, the “Test View” window is available in these rooms. Generally, the “Test View” window is the same in all “Medium” rooms. In the “Test View”, some options are made hidden or shown according to the needs. For example, in the “Differential” room, the “I diff” and “I bias” fields are available, while in the “Distance” room, the “[z,Left:0,Top:0,Right:0,Bottom:0,Scale:50%]” and “phi” fields are available.

Some parts like “Trigger” and “Binary Output” are the same in all rooms because changing their parameters was not deemed to be necessary. Those rooms which are used for testing the equipment are called “State Sequencer” and the windows available in the “Sequencer” rooms are, also, available in these rooms. Moreover, the “Instrument View” window, which is not available in the “Sequencer” rooms, is added to these rooms. Some windows including “Vector View” and “Signal View” are similar in all rooms and have the same structure but it is possible that some of their information is made hidden or shown according to the needs.

[\[jg1\]General_Types_of_Rooms](#)