



VEBKO ONLINE HELP

Software Installation

Category	tester
Section	Software Installation and Connection Setting
Language	English
Generated	2026-10-18

Vebko company's software comes in two versions of "Stable" and "Test". All the latest changes of the software are added to this version and, as the title suggests, it is a test version and may contain software bugs. Once these bugs are fixed, a stable version is released in which all the software issues are solved and it can be easily used. It, also, may not contain all features of the test version. Note that you can install both test and stable versions at the same time without facing any problem. To download the latest test or stable versions, you can visit the software section at www.vebko.ir.

It should be noted that, before installing the software, if an older version of the software is already installed on the currently being used system, to install a newer version, there is no need to uninstall the old version and the newer version will automatically replace the old one. To install the software, run the "Test.exe" file. Then, to continue, select "Next". It is necessary to install the "WinPcap" software before trying to install the Vebko software.



The screenshot shows the 'نرم افزار' (Software) section of the Vebko website. A hand cursor is pointing at the 'نرم افزار' tab. Below the navigation bar, there is a table titled 'دانلود آخرین آپدیت نرم افزار' (Download the latest software update). The table has five columns: 'دانلود' (Download), 'نسخه' (Version), 'نوع' (Type), 'عنوان' (Title), and an unlabeled column for the download count. There are three rows of software versions listed.

دانلود	نسخه	نوع	عنوان	
	۹۷.۱۲.۱۸.۰۰	Stable	Windows (XP, V, ۸, ۱۰)	۱
	۹۹.۰۳.۰۵.۰۱	Test	Windows (XP, V, ۸, ۱۰)	۲
	۹۷.۰۵.۱۶.۰۱	Stable	Android	۳

Figure 1



Figure 2

Click on "Next" option again. Then the WinPcap 4.1.3 Setup message will pop up which means that this software has been installed before and if it is necessary to reinstall it, select "Ok"; otherwise you can select "Cancel" to continue. If the software has not been installed on the currently being used system, the "Install" option will be available to install the WinPcap software. Now, in the opened window, check the "I agree" option and click on "Install". Installing the AMPro Test software takes a few seconds. Now you can run the software by clicking on the "Run" option. In the "Security" section on the main page of the software, by clicking on "Open Source Location", the location where the software is installed will be opened. On this page, right-click on the "AMPro Application.exe" file and select "Properties". Now, in the "Compatibility" tab, check the "Run this program as an administrator" option. Then, you need to repeat the same process for the "AMPro APP Launcher.exe" file.




Figure 3




Figure 4




Figure 5

After doing so, installation software process is finished and it can be use it for testing.



Figure 6

Software_Installation