



VEBKO ONLINE HELP

---

# Software Start Page

|           |                           |
|-----------|---------------------------|
| Category  | <b>tester</b>             |
| Section   | <b>Software Home Page</b> |
| Language  | <b>English</b>            |
| Generated | <b>2026-10-18</b>         |

The "Start" page of the software is the first page that you face when the software is opened. At the top right is the version name of the software ("Stable", "Test") as well as its version number. If a new version of the software is provided by Vebko, when you are connected to the internet, an option, saying "New Version is Available" will appear at the top right. By clicking on this option, you can download and install the latest version of the software. Clicking on the "What's New" option opens a page in which the fixes or the features added to different versions of the software are displayed. For preparing these versions, first, Vebko experts present the software problems and suggestions to the software group. Then, after evaluating and correcting this group, the new features are displayed in detail on this page.




Figure 1

By clicking on the "Launch Remote Help" option, you can connect to the online software support via one of the two available methods of "AnyDesk" or "Ammy Admin". For using AnyDesk, first, the user needs to give the 9-digit number called AnyDesk ID, which is available at the top left of the "New Connection" page, to the supporter. Then, the supporter will enter the code in the "Remote Desk" section and press "Connect" to connect to the user's "Desktop" page.



Figure 2




Figure 3

Also, by clicking on "Ammy Admin", the "Ammy Admin-Free" page opens. Then, the user needs to give their "ID" and "Password" to the supporter. After that, the supporter will enter this information and connect to the user's desktop.




Figure 4

The "Relay Modules" section contains the special software for Vebko's relay. In the "Tester Modules" section, different relay test rooms are on the left while equipment test rooms are on the right.



Figure 5

You can adjust the settings for all test pages by clicking on the "Preferences" option. In all rooms, you can see two letters and numbers at the top right of the screen:




Figure 6

1- "M" means that how many megabytes of the ram is occupied by this page.




Figure 7

2- "AS" which is "Auto Save" means that if you make a change to the file, after passing the time that is specified in front of this option, the software automatically saves the status of the file and if there is a previous file, the new file replaces the existing one. After the file is saved, a message saying "Auto Save Done" will be displayed at the bottom of the page.




Figure 8

The software repeats this saving process every 30 seconds which can be changed in the "Auto Save" section in the "Room" tab on the "Preferences" page. This saved file is displayed in the "Recovery" option. If the software crashes for any reason, by clicking on the "Recovery" option, you can recover and view the last saved version of your file. This is an advantage for the software because the "Ctrl+Z" key combination recovers the changes based on this 30 seconds and if the software crashes, the test file will not be destroyed.




Figure 9




Figure 10

By clicking on the "Security", two options open. "Clear Cache" option which is used to clear the cache of the software.




Figure 11

When you install the software for the first time, you should click on the "Open Source Location" option to run both "AMPro Application" and "AMPro APP Launcher" files as an administrator. To do this, right-click on the mentioned files, then select "Properties" and in the "Compatibility" tab, check the "Run this program as an administrator" option. After that, you can close the window.




Figure 12

The "Contact us" option provides you with ways to connect with experts at Vebko.



Figure 13

The "About" option, provides the user with information about Vebko company.




Figure 14

By clicking the "Help" option, provides the user with the reference manual and of the tester and the software.



Figure 15

Various tasks are performed in the "AMT" section. You can directly connect or disconnect to the device by holding on the "Control" button and left-clicking on this image. The figure in this section indicates the connection status to the device. By double-clicking on this section, it is possible to enter the "Preferences" page directly. If you want to connect to multiple devices at the same time, right-click on this section and select the device name to connect to it. By doing this, the device name will appear on the left of the screen.






Figure 16

[jg1]Software\_Home\_Page